

How to use Merci Wallet

[MAC OS users]



CONTENTS

01 ■■■ Install a Merci Wallet

02 ■■■ View a Merci Wallet



01

Installation of a Merci Wallet




1. How to install a wallet



1. How to install a wallet



1. Double-click the Merci-Qt.dmg file you downloaded .



2. Drag Merci Core to the Applications folder.



3. Press F4 to double-click the installed Merci Wallet icon.

02


View a Merci wallet




1. View the wallet configuration (general, master node)
 - 1-1. How to check nodes and to disable the sleep mode
2. Check my wallet address
3. Send coins
4. Check transactions
5. Encrypt a Merci wallet
6. Backup and restore a Merci wallet
7. Delete a Merci wallet




0. Check sync



the sync window that appears when you run the wallet



the status bar hiding the sync window




the status bar with completed sync

the number of remaining blocks: the number of remaining blocks until sync is reached

last block time: the last time when Merci coins was included


- sync guide windows can be hidden by the hiding button and it does not affect other operations of the wallet.

1. View a wallet configuration - General Merci wallet



- ① Menu (My wallet, Send, Receive, Transaction)
- ② My MERCI balance
- ③ View MERCI balance details (coins available, coins to be deposited, total coins in balance)
- ④ Quick view of transaction

1. View a wallet configuration - Master Node Merci wallet



- Stake coin: Coins for deposit purposes (the number varies depending on the process of taking a block)

- If there are more than 6 million coins available, the lightning bolt icon in the bottom status bar will be colored automatically.



General



Master Node

- ① Menu (My Wallet, Send, Receive, Transaction)
- ② My MERCi balance
- ③ View MERCi balance details (coins available, coins to be deposited, Stake coins, total coins in balance)
- ④ Quick view of transaction
- ⑥ Lightning bolt icon in black


1-1. How to check the node and to disable the sleep mode



How to check the node connection

1. Run the wallet.
2. Click the Help - Debug Window - Peer tab in the top status bar.

- If the numeric address is connected to the peer tab as shown in the figure, the normal connection is established with the POS.



Notice

- The numeric address has to be connected to the peer tab in order to enable POS dividends.
- POS dividends is possible only if the computer is turned on and the wallet program is run.
- When the computer is in the sleep mode, it cannot process POS dividends (need to disable the sleep mode)
- It is possible to change the numerical address and details of the nodes connected to the peer tab.

1-1. How to check the node and to disable the sleep mode


How to disable the sleep mode



1. Open System Preferences




2. Click Energy Saver



3. Drag the display off bar to 'Never'
4. Check 'Prevent computer from sleeping automatically when the display is off'

2. Check my wallet address




1. Click the File menu.
2. Click Receiving addresses.
3. Click the New Item button to create a wallet address.



- Click on the New (N) button to create an additional wallet address.

3. Send coins



1. Click the Send menu.

2. Enter a coin and the MERCRI wallet address of the receiver and choose a label, an amount, and a fee waiver option.

3. Set the transaction fee and click the Send button.

Notice

- It is recommended to send the transaction fee with the default setting, Recommended.

- Coins may not be transferred if the fee is set to less than 0.004 MERCRI when setting in Custom.

- Please double-check whether the other person's MERCRI wallet address is correct. Due to the nature of the coin, you cannot cancel your transfer after you click Send.

- The label is a memo that helps you to remember. It is optional, so the coin transfer is possible without it.

- If you click on 'fee deducted from the remittance', only the amount of coins from which the fee is subtracted will be sent to the other party.

(ex) When you send 1 MERCRI, if you choose 'fee deducted from the remittance', the receiver will only receive the amount of coins resulted from subtracting the fee from 1 MERCRI.


- Approval Time Target is an option to adjust the number of coin confirmation.

- What is the difference between Recommended and Custom?

Recommended: A coin transfer method with a default fee

Custom: A coin transfer method with an adjustable fee, the higher the fee, the faster the transfer rate

4. Check transactions




1. Click the Transactions menu.
2. You can search for a desired transaction by specifying a search format.(All of coin transmittance and coin remittance records are displayed.)

- If you do not specify a search format, transaction confirmation for all transactions is possible.

5. Encrypt a Merci wallet



1. Click the Setting menu.
2. Click the Encrypt Wallet menu.
3. Enter your secret password to encrypt your wallet.



Notice

- The secret password must be set to 10 or more random letters or 8 or more words.
- When you lose your secret password, there is no way to recover the Merci wallet.
- When you set a secret password, you can set the secret password with case sensitive.
- The password is not accessible even from the Merci administration team, so please be careful about security, keeping the chosen password in a separate place. You will not be able to recover your secret password once you lose it.


5-1. Merci wallet encryption and POS setting




If you run the wallet and do not unlock it after setting Merci encryption, it cannot be connected to POS.
Follow the steps below to unlock it and confirm that it is properly connected to POS.



Locked Merci Wallet



1. Click Settings-Unlock Wallet.



2. Enter the password you set and click the OK button.



- For staking only: The encryption is unlocked only for a POS connection. When you send a coin, you will be asked to enter a password.



Unlocked Merci Wallet

After unlocking it through the above process, the lightning bolt icon will automatically appear in black when the number of Merci you possess is 6 million or more.

6. Backup a Merci wallet






Notice

1. Click the File menu.
2. Click the Backup Wallet menu.
3. Select the path to back up your wallet.

- The wallet backup is safe after you select the encryption option.
- For the wallet backup file storage locations, external hard drives or a USB is recommended excluding the desktop and the C drive.

6. Restore a Merci Wallet



1. Click the File menu.
2. Click the Restore Wallet menu.
3. Click ... button.
4. Find the backup file of your wallet and select it.


Notice

- If you lose your secret password, there is absolutely no way to restore your wallet even if you have the wallet.dat file or the backup file.


7. Delete a Merci wallet - Delete applications




1. Click finder.



2. Click an application



3. Select the Merci Core file and right-click.



4. Click 'Move to Trash' to delete.

Notice

- The above method is a primarily method to delete the Merci wallet application. Please refer to the following chapter to delete both blocks and data.

7. Delete a Merci wallet - complete deletion of data and block



1. Start terminal.

```
gimseulgi — -bash — 80x24
Last login: Fri Oct 19 10:18:23 on ttys000
gimseulgis-iMac:~ gimseulgi$
```

Commands to enter

cd ~/Library/Application Support

Input the commands and press Enter

2. Enter the command. (Please keep spacing and capital letters in English)

```
gimseulgi — -bash — 80x24
Last login: Fri Oct 19 10:18:23 on ttys000
gimseulgis-iMac:~ gimseulgi$ cd ~/Library/Application Support
-bash: cd: /Users/gimseulgi/Library/Application: No such file or directory
gimseulgis-iMac:~ gimseulgi$
```

Commands to enter

rm -rf Merci

Input the commands and press Enter

3. If the above screen appears, enter the command again. (Please keep spacing and capital letters in English)

All the blocks and data remaining on the computer have been deleted.

Notice

- If you reinstall the Merci Wallet without completely removing it as shown above, the existing data may remain and the program may not work normally.

THANK YOU

